



Express Tools Guide

GstarCAD 2027



Table of Contents

1. Block Tools	1
2. Text Tools	10
3. Layout Tools	13
4. Dimension Tools	14
5. Selection Tools	18
6. Modify Tools	22
7. Draw Tools	30
8. Tools	34
9. Table Tools	36
10. Coordinate Tools	42
11. Drawing Tools	44
12. AutoXlsTable	50
13. GstarCAD Tools	54
14. Plot Tools	59

Express Tools

The GstarCAD Express Tools contain a library of productivity tools designed to help you extend the power of your design. They are easy to use, easily integrated into your menus and toolbars, and cover a wide range of functions, including dimensioning, drawing, and selecting and modifying objects. GstarCAD Express Tools are organized on:

1. Block Tools

Change Base: The CHANGEBASE command allows changing the base point position of a block. You can move the base point and keep objects staying in same position, or move objects and keep base point staying in same position.

Menu: Express>Blocks>Change Base

Command Entry: CHANGEBASE



Block Break: Working with block references that represent symbols are essential in some industrial application drawings like electrical schematics, piping, etc.

But a headache comes when try to place these blocks accurately overlapping or even breaking other objects on your drawing. Now get rid of this headache with BLOCKBREAK command. This innovative tool is able to wipeout or breaks an object that is overlapped by a reference block.

For example, insome cases we may need to insert block symbols into a cable line in electrical schematic. And normally the cable line is required to be broken by the symbols at where the symbols are inserted. Similar request are also exists in other application designs.

Menu: Express>Blocks>Block Break

Command Entry: BLOCKBREAK

Block break dialog box:

Name: List all available blocks created in the drawing.

Browse: Browse to open specific drawing file.

Pick: You can pick an existing block reference in the current drawing.


Scale: Scales the block reference size according to X, Y and Z coordinates. Uniform Scale option keeps the original size of block reference.


Rotation: You can rotate a block reference by inputting an angle value or keep aligned.

Process Mode: You can use a block reference to break or wipeout objects when overlapping.


Block Break Process Mode Illustration

Break: Breaks background object(s) when a block reference is overlapped.





Wipeout: Wipeout background object(s) when a block reference is overlapped.



Replace Block with Another Block: In the current drawing, you can use one block to replace another one. Moreover, you can purge the unreferenced block when the operation is finished.




Menu: ExpressTools>Blocks>ReplaceBlock

Command Entry: BLOCKREPLACE

Select a block to replace: Double bed. Then select: OK

Select the block to be replaced: Sofa. Then select: OK

Purge unreferenced items when finished? Yes/No



See the result:



Copy Nested Objects: Copy objects in an xref or a block.

Menu: Express>Blocks>Copy Nested Objects

Command Entry: NCOPY

Command line prompts as follows:

Select nested objects to copy: Use an object selection method

Base point: Specify a point, or enter M for multiple copies

Specify second point or <use first point as displacement>: Specify a point

Explode Attribute to Text: Explode blocks, converting value of attributes to text objects.

Menu: Express>Blocks>Explode Attributes to Text

Command Entry: BURST



Command line prompts as follows:

Select entities: Use an object selection method

For example: Explode attributes and convert them to text objects.

1. Select a block containing two attributes.

2. Block exploded and attribute values converted to text.




Attribute Increment: ATTINC command helps to specify attribute of blocks with incremental value, and to modify attribute value of blocks according to the sort method.

Menu: Express>Blocks>Attribute Increment

Command Entry: ATTINC

This command can increase block attribute value that contains a number or letter. When ATTINC command is on, as long as the drawing is not closed, when copying, inserting and deleting a block attribute in the drawing, the property number or letter can be updated automatically.



Export Attribute Information: Export block attribute to an external file in tab-delimited ASCII format.


Menu: Express>Blocks>Export Attribute Information

Command Entry: ATTOUT

Once performed ATTOUT command, specify file name and save path in "Enter output filename" dialog box, then command line prompts:

Select entities: Specify the blocks whose attributes you want to export.

The block names and attributes are exported to the named file. If the file already exists, you are prompted before it is overwritten. You can easily view attributes in a spreadsheet format and edit individual attribute values. Then you can enter the new values into the drawing file, using the ATTIN command.



Import Attribute Information: Import block attribute to an external file in tab-delimited ASCII format.



Menu: Express>Blocks>Import Attribute Information

Command Entry: ATTIN

Using ATTIN and ATTOUT together, you can quickly make changes to attribute values for selected block references.

Once this command is performed, the "Enter input filename" dialog will pop up for the user to search file, import the block attributes along with the same handle and block name into the drawing, and make changes to the block attributes as well.

Once an attribute value is modified, it will be




integrated into the specified block. It should be noticed that the imported file can't be attribute file exported by ATTOUT command, whereas the file format should be identical to that of ATTOUT command exporting.

Reads through imported file and processes each line when performing ATTIN command. If the block with the same handle and name is found in the process of treating lines, the modified attribute value of this block will be applied. If several blocks with the same handle and name are found, then system prompts whether to interactively assign saving data when processing these blocks. If "Yes" is selected, the data of each command line will be listed enabling selection of a block to apply this attribute. Press ENTER to skip to next line, press ESC to exit.

Edit Block Attribute in Place: Allows you to edit the textual contents of an attribute of a block when you feel like editing the attribute values without accessing the attribute editor.

Menu: Express>Blocks>Edit Block Attribute in Place

Command Entry: ATTIPEDIT




Statistics Blocks Number: You can statistics the quantity of various blocks through this function.

Menu: Express>Blocks>Statistics Blocks Number

Command Entry: BLKNUM

Once this command is performed, its dialog box will pop up. Under Stat. Condition, you can input a block name, layer or check the options: Ignore the blocks in the same insert point and also ignore the scale.




Count Blocks: This function is used to count the number of the blocks by list.

Menu: Express>Blocks>Count Blocks

Command Entry: BCOUNT

Operation steps:

1. Start the command, the command line prompts *"Enter to select all blocks or ..."*.
2. You can press enter to select all the blocks within the drawing or by selecting blocks.
3. Once pressing "Enter" the system will display the result in the command line.




Change Block Color: Modify the block color quickly.

Menu: Express>Blocks>Change Block Color

Command Entry: bChgCol

Operation steps:

1. Start the command.
2. Input new color number, here we input 30 for example.
3. Select block objects, for which the color needs to be changed.
4. Finished modifying.




Change Block Linewidth: This function can modify block linewidth quickly.

Menu: Express>Blocks>Change Block Linewidth

Command Entry: bChgWid

Operation steps:

1. Start the command.
2. Input a new line width value.
3. Select block objects, for which the line widths need to be changed.
4. Finish changing the line width.




Change Block Text Angle: This function can change the text rotation angle of the block and it only takes effect on text or mtext, attribute text can't be changed.

Menu: Express>Blocks>Change Block Text Angle

Command Entry: bChgAng

Operation steps:

1. Start the command.
2. *Input new text angle(comparative with @) <0>:* input 0.
3. *Select the block to change text angle:* then *Select objects:*
4. Finish changing the text angle.




Change Block Text High: This function can change the height of the block, it only takes effect on text or mtext, attribute text can't be changed.

Menu: Express>Blocks>Change Block Text High

Command Entry: bChgHei

Operation steps:

1. Start the command.
2. Input a new text height value.
3. Select objects whose text heights need to be changed.
4. Enter to finish the command.




Change Block Layer: This function can change the block layer.

Menu: Express>Blocks>Change Block Layer

Command Entry: bChgLay

Operation steps:

1. Start the command.
2. Input target layer name.
3. Select block objects to change layer.
4. Press Enter. If the target layer exists, the selected block will be moved to the target layer, if a target does not exist, the software will make a new layer automatically and move the block object to the new layer.




Convert BLOCK to XREF: Replace all instances of a standard block with an xref. Unbind xrefs that are bound.

Menu: Express>Blocks>Convert Block to Xref

Command Entry: BLOCKTOXREF


-BLOCKTOXREF searches the entire drawing for references to a specified block name and replaces them with an xref that you specify. You can have



the unreferenced block purged when done. In BLOCKTOXREF dialog box. Select a block to replace: Table and 4 chairs. Then select OK button.

-In Select a Xref file. Select the Xref you want. Then select Open button.

Purge unreferenced items when finished? Yes/No




List Xref/Block Properties: List the type, block name, layer name, color and linetype of a nested object in a block or an xref.

Menu: Express>Blocks>List Xref/Block Properties

Command Entry: XLIST

Command line prompts as follow: *Select nested xref or block object to list:* Use an object selection method. After selecting an external reference, the "Xref/Block object" dialog box will display attributes of specified blocks and xref, including object type, block name, color and linetype.



Trim to Nested Objects: Trims objects with a block as a cutting boundary.


Menu: Express>Blocks>Trim to Nested Objects

Command Entry: BTRIM

Command line prompts as follow:

-*Select objects or <select all>:* Select one or more blocks and press ENTER.

-*Select the object to Trim or Shift-select to Extend or [Edge/Fence/Crossing/Project]:* Select object(s) or enter an option and press ENTER.




Extend to Nested Objects: Extends objects such as line segment, arc, polyline or ray to a block. Objects would be extended to a block as close as possible if they cannot intersect with each other.

Menu: Express>Blocks>Extend to Nested Objects

Command Entry: BEXTEND

Command line prompts as follow:

-*Select objects or <select all>:* Select one or more



blocks and press ENTER.

-Select the object to Extend or Shift-select to Trim or [Edge/Fence/Crossing/Project]: Select object(s) or enter an option and press ENTER.


External Reference Relocate: With this function, our software can recognize the reference in the drawing and give you the reference state, if you want to select another reference path, click the “Relocate” button and the reference will be displayed in the drawing again.

Menu: Express>Blocks>External Reference Relocate

Command Entry: CHGXREFPATHa

Operation steps:

1. Start the command and a dialog box will pop up.
2. Select the external reference name which you want to modify.
3. If you click the “Relative Path” button, you will get a relative path of the reference; If you click “Relocate” button, the system will relocate the external reference.



2. Text Tools

Justify Text: Change a text object's justification without changing its position. Works with text, mtext, and attribute definition objects.

Menu: Express > Text Tools > Justify Text


Command Entry: TJUST

Select objects: Use an object selection method.

[Start/Center/Middle/Right/TL/TC/TR/ML/MC/MR/BL/BC/BR] <Start>: Choose the new justification

Usage Example: Covert text to middle justified

-Text left justified.



TEXTOUTLINE
EXPLODE

-Text after justification change.



TEXTOUTLINE
EXPLODE

Rotate Text: Aligns text, mtext and block attribute objects to new orientation. Rotates text, mtext, and attribute definition objects so that they end up being as close as possible to horizontal or right-read (similar to the behavior of dimension text). Objects are rotated about their middle point in 180-degree increments. For example, if the text is upside-down, it becomes right-side up after a TORIENT operation. Similarly, left-read text becomes right-read text.

Menu: Express > Text Tools > Rotate Text


Command Entry: TORIENT

-*Select objects:* Use an object selection method

-*New absolute rotation <0>:* Enter a new absolute orientation angle for all selected text.

Usage Example: -Text before rotation

-Text after rotation specified angle of 0 degrees




Change Text Style: This function can change current text style for specified text and single line text, multiline texts are available.

Menu: Express > Text Tools > Change Text Style

Command Entry: CHGSTY

Operation steps:

1. Start the command.
2. Select the text to change text style and you can modify several objects at a time. Then Press enter to finish the command.



Chinese Characters Split: This function can split single line texts to single text one by one, because the English word is a

combination of several letters. This function only makes sense for Chinese Characters.


Menu: Express > Text Tools > Chinese Characters Split

Command Entry: HZCF

Operation steps:

1. Start the command.
2. Select the text to be split.
3. Press enter to finish splitting.

Text Text



Character Break: Breaks at the specific position without splitting the text into single-character, which is suitable for all single-line text.

Menu: Express > Text Tools > Character Break

Command Entry: TXTBREAK / WZDD

Operation steps:

1. Start the command.
2. Select the text to break.
3. Specify the position for the break.

Change Character: This function can continuously revise multiple text objects, single line and Mtext are applicable.


Menu: Express > Text Tools > Change Character

Command Entry: _DDEDIT

Operation steps:

1. Start the command.
2. Select the text to be replaced.
3. Input characters to replace and press Enter to finish.

Texx *Test*



Change One Character: This function can change texts in selected single line texts, you can just input characters to be replaced and characters to replace according to the prompts, Moreover it can be used in several single line texts at the same time.


Menu: Express > Text Tools > Change One Character

Command Entry: CHGTX

Operation steps:

1. Start the command.
2. Select the text to be replaced.

Text *Tool*



3. Input the characters to be replaced.
4. Input characters to replace.
5. Press enter to finish.

Change Text Height/Width/Angle/Position: This function is used to modify text height, text width, text angle and text position. You can click or select characters by window selection.

Menu: Express > Text Tools > Change Text Height/Width/Angle/Position

Command Entry: TXTHEI / TXTWID / TXTANG / TXTPOS

Delete Annotation: This function is based on this kind of circumstance, you can select one text annotation to be deleted, the software will register all the annotations in one layer, you can just press enter and all the text annotations will be deleted or you can select the texts by window selection and it will not affect the texts of other layers.

Menu: Express > Text Tools > Delete Annotation

Command Entry: WZOFF

Operation steps:

1. Start the command.
2. Specify a text annotation to be deleted. At this time you only specify the operation layer, if you directly press enter, the entire layer single texts will be deleted.
3. Select annotations to be deleted (you can select several objects by window selection) and press enter to finish.

Adjust Character: When the texts are mixed with Chinese characters, English letters and Arabic numerals, the text height will be different and the visual effect is not good. You can use this function to match the text height, but this function will explode the text's and it will be difficult to re-edit, so we suggest using this function after the user finished editing the drawing.


Menu: Express > Text Tools > Adjust Character

Command Entry: TTL2

Operation steps:

1. Start the command.
2. Select the text object which needs to adjust the height.
3. Press enter to finish.

GstarCAD
G s t a r C A D



Glossary Storeroom: Opens "Glossary Storeroom Manager" dialog box.

Menu: Express > Text Tools > Glossary Storeroom

Command Entry: chkck

3. Layout Tools

Align Space: Adjust the zoom and pan factor of in the layout viewport based on the alignment points specified in the model space and paper space.

Menu: Express > Layout Tools> Align Space

Command Entry: ALIGNSPACE

List Viewport Scale: Displays the scale of the current viewport or of a selected layout viewport.

Menu: Express > Layout Tools> List Viewport Scale

Command Entry: VPSCALE

Synchronize Viewports: Synchronize one or more layout viewports to a master layout viewport to have the exact locations matched up. All synchronized viewports use the zoom factor of the master viewport.

Menu: Express > Layout Tools> Synchronize Viewports

Command Entry: VPSYNC

Merge Layout: Merges specific layouts into a single layout. All layouts or model are available to be picked, and you can specify an existing layout or enter a new name to create a new layout as the destination layout.

Menu: Express > Layout Tools> Merge Layout

Command Entry: LAYOUTMERGE


4. Dimension Tools

Area Table: AREATABLE command automatically dimension and count the area of an enclosed object and export the result to a table in the current drawing area.

Menu: Express>Dimension>AreaTable

Command Entry: AREATABLE

The enclosed area or object can be marked with a number or area symbol, and the area table data can be generated at the same time. The area data can be exported to a text or table file. The values in the table can be changed automatically when the number or area size is changed.



Rapid Dist: Measures distance and angle between 2D objects along X, Y axis rapidly by moving mouse.


Menu: Express>Dimension> Rapid Dist

Command Entry: RAPIDDIST


Distances that only can be measured along X, Y axis based on the position of your mouse, are displayed dynamically as you move your mouse over and between objects. Angles between the objects touched by distance lines, are displayed dynamically at the same time.

The command only can be used under WCS, and only measure the 2D objects. And the angles of the blocks can't be measured.

Type **"Settings"**, you can set unit conversion and scale in setting window.



Type **“Record”**, you can save the current result in command line window, which is convenient to check or copy data to other documents.




Change Dimension Text: Change the dimension content into the specified value.

Menu: Express>Dimension>Change Dimension Text

Command Entry: CHGDIMTXT

Command line prompts as follows:


- Select dimension objects:* Select a dimension
- Currently label content <129.9>, input new dimension text <practically measure dimension>:* Type a new value (130)



Change Dimstyle: Apply the current dimension style to the dimensions in the drawing.

Menu: Express>Dimension>Change Dimstyle

Command Entry: Dimstyle




Reset Dim Text Value: Restore a measurement value to overridden or modified dimension text.

Menu: Express>Dimension>Reset Dim Text Value

Command Entry: DIMREASSOC

Command line prompts as follows: *Select object:* Select dimension objects with non-associative text or press ENTER to quit.



Update Dimension: Updates any other dimension(s) to the current dimension style you want to apply.


Menu: Express>Dimension>Update Dimension

Command Entry: DIMUPDATE

Command line prompts as follow:

- Select a dimension for standard:* Select a dimension as a base.

-Select a dimension, ensure update the dimension style: Select dimension(s) to be update.



Dimstyle Export: Exports named dimension styles and their settings to an external file.

Menu: Express>Dimension>Dimstyle Export

Command Entry: DIMEX



Executing this command, starts the following dialog box:

Export Filename: Creates a DIM file. Enter the DIM file name or select Browse to locate the file. If the file does not exist, it is created. If the file does exist, a prompt requests permission to overwrite. The new file is an ASCII file.

Available Dimension Styles: Selects the dimension styles to write to the ASCII file. The current dimension styles are displayed. Each selected style is written to the file indicated in the Export Filename group.

Text Style Options: Saves either the dimension's Full Text Style Information or the Text Style Name Only to the ASCII file.

Note: Dimstyles are created and saved with the DDIM command. You must select at least one Dimstyle for the export to be successful.



Dimstyle Import: Imports named dimension styles from a DIM file into the current drawing.



Menu: Express>Dimension>Dimstyle Import

Command Entry: DIMIM

Executing this command, starts the following dialog box:

Import Filename: Names the file you want to import. Enter an existing file name or select Browse to specify a DIM file to import. The file must be of the form generated by the corresponding DIMEX command. All dimension styles in the selected file are imported into the current drawing. Text styles are also imported.

Import Options: Includes Keep the Existing Style, to keep the dimension style in the current drawing and Overwrite Existing Style, to overwrite styles in the current drawing. The Keep the Existing Style option ignores the similarly named style being imported; Overwrite Existing Style uses the similarly named style being imported.



Attach Leader to Annotation: Attach leader line to Mtext, tolerance, or block reference object.


Menu: Express>Dimension>Attach Leader to Annotation

Command Entry: QLATTACH

Use the QLATTACH command to attach leaders to Mtext

-*Select Leader:* Select a leader

-*Select a dimension:* Select the Mtext, tolerance, or block reference object for the annotation.



Usage Example:

-Select a leader, and then specify the Mtext object to attach.

-Separate leader line and Mtext objects.

-Leader line with mtext attached as one object.

At the *Select Leader:* prompt, you will be prompted until you select a leader object or abort the command.

At the *Select Annotation:* prompt, you will be prompted until you select an MText, Tolerance, or Block Reference object for the annotation.

Detach Leaders from Annotation: Detach leader line from mtext, tolerance, or block reference object.


Menu: Express>Dimension>Detach Leaders from Annotation

Command Entry: QLDETACHSET

-*Select objects:* Select leader line.

Usage Example:

-Select a leader line to detach from an mtext object.



Global Attach Leader to Annotation: Globally attaches leader lines to mtext, tolerance, or block reference objects.

Menu: Express>Dimension>Global Attach Leader to Annotation

Command Entry: QLATTACHSET

-*Select objects:* Select one or multiple leader lines and annotation objects.



Usage Example:

-Select leader line(s), and mtext objects to attach.

-*Select objects:* Select one or multiple leader lines and annotation objects, the command line prompts: Number of unlocked leaders = 2, Number with annotation detached = 2

-Leader with detached Mtext object

-Leader attached to block object

5. Selection Tools

Get Selection Set: Create a temporary selection set of objects.

Menu: Express>Selection>Get Selection Set

Command Entry: GETSEL

-*Select an object on the Source layer:* Use a selection set method or press ENTER for all layers.

-*Select an object of the Type you want:* Use a selection set method or press ENTER for all object types.

Fast Select: Selects the object that touches the specified object.

Menu: Express>Selection>Fast Select

Command Entry: FASTSEL

You can input FASTSEL command to select all objects that touch the selected object immediately.



Supported objects include: Lines, polylines, circles, arcs, attribute definitions, text, Mtext, ellipses, and images.

FSMODE: Controls two behaviors of FASTSEL command, default value is OFF.


If FSMODE is turned OFF, when you execute the FASTSEL command, it selects only those objects that are touching the selected object.

If FSMODE is turned ON, when you execute the FASTSEL command, it selects all the objects that are touching the selected object, as well as any objects that are touching those objects. The selection process of all unselected touching objects continues until there are no more unselected objects visible in the drawing area.

Filtrate Selection: Select, edit, and name filters for object selection.

Menu: Express>Selection>Filtrate Selection

Command Entry: Filter



Select Object Filter dialog box Options:

1. **X, Y, Z Parameters:** Defines additional filter parameters depending on the object. In the filter parameters, you can use relative operators such as < (less than) or > (greater than).
2. **Select:** Displays a dialog box listing all items of the specified type in the drawing. Select the items to filter.
3. **Add to List:** Adds the current Select Filter property to the filter list. Filter properties that you add to the unnamed filter remain available during the current work session unless you manually delete them.
4. **Replace:** Replaces the filter property selected in the filter property list with the one displayed in Select Filter.

5. **Add Selected Object:** Adds one selected object in the drawing to the filter list.
6. **Edit Item:** Moves the selected filter property into the Select Filter area for editing. To edit a filter property, select it and choose Edit Item. Edit the filter property and choose Substitute. The edited filter replaces the selected filter property.
7. **Delete:** Deletes a selected filter property from the current filter.
8. **Clear List:** Deletes all the listed properties from the current filter.
9. **The filter name is used:** Displays, saves, and deletes filters.

10. **Current:** Displays saved filters. Select a filter list to make it current. The named filter and its list of properties are loaded from the default file, filter.nfl
11. **Save As:** Saves a filter and its list of properties. The filter is saved in the filter.nfl file. Names can contain up to 18 characters.
12. **Delete Current Filter List:** Deletes a filter and all its properties from the default filter file.
13. **Apply:** Exits the dialog box and displays the Select Objects prompt, where you create a selection set. The current filter is used on the objects you select


Get Selection by Block Name: You can use this function to multi-select objects with the same name in specified area.

Menu: Express>Selection Tools>Get Selection by Block Name

Command Entry: GETBLKSEL

Operation steps:

1. Start the command.
2. Select object, specify a block name for operation.
3. Specify the region.
4. System will bring all the blocks with same name in region selected area into the selection.




Get Selection by Object Type: You can use this function to multi-select objects with the same entity type in specified area.

Menu: Express>Selection Tools>Get Selection by Object Type

Command Entry: GETENTSEL

Operation steps:

1. Start the command.
2. Select object and system will take the specified entity type as target type. Then specify region.
3. System will bring all the blocks with same entity type in region selected area into the selection.




Get Selection by Layer: You can use this function to select all the objects in specified layer and specified region at one time.

Menu: Express>Selection Tools>Get Selection by Layer

Command Entry: GETLAYSEL

Operation steps:

1. Start the command.
2. Specify an entity which is in the target layer, then specify region.
3. System will select all the objects in specified layer and specified region.



Get Selection by Color: Quick select the objects with the same color.

Menu: Express>Selection Tools>Get Selection by Color

Command Entry: GETCOLSEL

Operation steps:

1. Start the command.
2. Select one object and system will take the object's color as target color.
3. Specify region.
4. System will select the objects which have the same color as the target object automatically.

Get Selection by Object/Layer: Select entities by entity type and layer.

Menu: Express>Selection Tools>Get Selection by Object/Layer

Command Entry: GETENTLAYSEL

Operation steps:

1. Start the command.
2. Select one object and system will take the object layer as target layer.
3. Specify region.
4. System will select the objects which are in the same layer and with same entity type automatically.

Get Selection by Object/Color: Select entities by entity type and color.

Menu: Express>Selection Tools>Get Selection by Object/Color

Command Entry: GETENTCOLSEL

Operation steps:

1. Start the command.
2. Select one object and system will take the object's color as target color.
3. Specify region.

4. System will select the objects which have the same entity type and color as the target object automatically.

Get Selection by Layer/Color: Select entities by color and layer.

Menu: Express>Selection Tools>Get Selection by Layer/Color

Command Entry: GETLAYCOLSEL

Operation steps:


1. Start the command.
2. Specify an entity which is in the target layer.
3. Specify region.
4. System will select the objects which have the same color and same layer as the target object automatically.

6. Modify Tools

DWG Units: DWGUNITS command allows you to change the units of drawings to meet the standard size and annotation requirements of the drawing and avoid errors due to using different units.

Menu: Express>Modify> DWG Units


Command Entry: DWGUNITS



Layer Draworder: Rearranges the layer order to adjust the sequence of the objects.

Menu: Express>Modify> Layer Draworder

Command Entry: LAYDRAWORDER



Draworder by Color: Arranges the drawing order of selected objects by their color number.


Menu: Express>Modify> Draworder by Color

Command Entry: CDORDER

Break Object: In some industrial application design, sometimes we need to break pipes or cable lines in our schematic drawing to indicate their spatial relationship. Sometimes we also need to break lines at crossing point to make it convenient for the later edit. Break Object tool came from this kind of needs.

Menu: Express>Modify> Break Object

Command Entry: BREAKOBJECT



This tool provides four breaking modes with gap distance to visualize the differences between breaking options.


Gap: Indicates the gap value between broken objects

Break all objects selected with each other: This option breaks all intersected objects each other. You can select objects by window selection or picking each object.

Break selected objects with other selected objects: This option breaks all intersected objects by two selection sets (A and B). The objects selected under the first set (A) will be broken meanwhile the objects selected under the second set (B) will be not broken.

Break objects touching selected objects: This option breaks all intersected objects that touch at first instance selected object.

Break selected objects with any objects that touch it: This option breaks the first instance selected object with all intersected objects to it.



Move/Copy/Rotate: Move, copy, rotate, and scales object(s) with a single command.


Menu: Express>Modify>Move/Copy/Rotate

Command Entry: MOCORO

Command line prompts as follow: **Select objects:** Select object(s) and press Enter

Base point: Specify a base point

[Move/Copy/Rotate/Scale/Base/Undo] <eXit>: Once an option is specified



Options

Move: Move object(s). **Copy:** Make multiple copies of object(s). **Rotate:** Rotate object(s). **Scale:** Dynamically scale object(s).

Base: Specifies a base point for object(s) to be moved, copied, scaled or rotated.


Region Scale: You can select a region of a drawing to be cut and copied to a new location.

Menu: Express>Modify>Region Scale


Command Entry: _REGSCALE

Command line prompts as follow:


Specify left up corner point for full-page proof: Select a region from left up to right down corner




Specify the position to copy: Specify any place you want to copy to the selected region



Select the object to Trim or shift-select to Extend or [Edge/Fence/Crossing/Project]:
Select objects to trim or press Enter to finish the operation.



Input zoom scaling, the block and text will zoom together <Enter- No Zoom>: Press Enter to finish the operation.




Trim Enhancement: Trim one side of an object which is intersecting with other objects. The object can be polyline, line, circle, arc, ellipse, image or text.

Menu: Express>Modify>Trim Enhancement

Command Entry: EXTRIM

Operation steps:

1. Start the command.
2. Select an object as trim reference, here we select the rectangle for example.
3. Specify the side to trim on.
4. Here we select the internal point of the rectangle, you will see that the internal lines of the rectangle are trimmed.



Extended Offset: This enhanced version of the OFFSET command offers several advantages over the standard command, including layer control, undo, and a multiple option.

Menu: Express>Modify>Extended Offset

Command Entry: EXOFFSET


1. *Specify offset distance or [Through] <T>:* Specify the offset distance or through point
2. *Select object(s) to offset or [Options/Undo]:* Select an object to offset, change options or undo
3. *Specify an option to set [Distance/Layer/GapType]:* Specify an option

EXOFFSET Options:

Distance: Specify the offset distance or through point

Layer: Specify the layer for new objects. Current Layer or Source Object Layer

GapType: Sets or changes the offset mode as controlled by the OFFSETGAPTYPE variable. The options are: Normal, Fillet or Chamfer.



Multiple Pedit: This command is almost the same as the standard command.


Menu: Express>Modify>Multiple Pedit

Command Entry: MPEDIT


1. Start the command.
2. *Select object*
3. Specify an option to set *[Open/Close/Decurve/Fit/Linetype-mode/Spline/Width/eXit] <eXit>*:

Example to close plines:

1. *Select object*: select plines which you want to close.



2. *[Open/Close/Decurve/Fit/Linetype-mode/Spline/Width/eXit] <eXit>*: Input keyword: C and enter.
3. You will get the plines closed.



Extended Clip: Clip images, xrefs, wipeout, or specified parts of block objects using circles, arcs, ellipses, or text as boundaries.

Menu: Express > Modify > Extended Clip

Command Entry: CLIPIT


The regular clipping (CLIP) command does not support clipping raster images with circle, arc, or ellipse boundaries, while the CLIPIT command supports clipping images, xrefs, wipeout, or specified parts of block objects using circles, arcs, ellipses, or text as boundaries and you can set the maximum error distance of the curve approaching.

Delete Duplicate Objects: This function can not only manage overlapped lines, circles, Plines linear objects etc, but can also manage entire coincident blocks, texts, dimensions and regions .Moreover, remove does not simply mean delete, it judges by layer, color, line type and many relevant attributes and can delete or connect coincident parts of 2D and 3D Plines, circles, arcs and overlapping line parts. Using this option can not only delete redundancy objects, but can also avoid editing and printing problems caused by overlapped objects.

Menu: Express > Modify > Delete Duplicate Objects

Command Entry: OVERKILL

- Start the command and the command line prompts as follow: *Select objects*: Select the objects to be compared and deleted. In the overkill dialog box, you can set-up the object comparison, comparison precision (distance between objects) and the object type. After selecting the options according to your need, select OK.



Multiple Copy: Copy multiple objects with Repeat, Array, Divide and Measure options.

Menu: Express>Modify>Multiple Copy

Command Entry: COPYM

Start the command and the command line prompts as follow: *Select objects:* Select the objects to be copied

Base point: Specify a base point


Second point or [Repeat (last)/Divide/Measure/Array (dynamic)/Undo] <exit>: Select a second point or any option

Options:


Repeat: Repeat the last copy using the same offset distance.

Divide: Linear divide option. Prompts for an additional point and the number of copies to make. Makes evenly spaced copies of the selected objects between the base point and the second selected point

Repeat




Divide




Measure: Linear measure option. Prompts for an additional point and the distance between copies. Makes evenly spaced copies at the specified distance between the base point and the second selected point.

Array: Displays the Array Options prompt.



Measure



Array

Layout By Path: Unlike common array function, LayoutByPath distributes object copies along a path (curve) with a variety of array options. Users can choose random, division and measure options and array in different directions along the path.


Menu: Express>Modify>Layout by path

Command Entry: Layoutbypath

For example, on mapping drawing, we can apply this tool to array the discontinuous central axis of the road or highway as shown in the picture:




After started the command Layoutbypath, a message will display in the command line>*Please select the object to array:*



After select the object, a prompt message will display:

Please specify the base point:


The base point is the point where you want to start doing array from the object. We can select the low left end point of this object:



After select base point of the object, a prompt message will display:

Specify the object's direction along the curve<Y axis of WCS>:


This message is important because this will play with the object's direction along the path. Because we select the end low point of the object as base point, we have to specify a parallel point direction to keep the object parallel along the path (long green line):



After specify the object's direction, a prompt message will display:


Please select the curve:

Then select the long green line. This line is the curve or path that the object will follow.



After select the curve or path, a prompt message will display:

Specify select along which side of the curve <left side or forward direction>. This message is also important because we will specify the side which the object will be array. For example, we specify left side of the curve as shown in the picture.



After specify the side of the curve, a prompt message will display: *Select the method Random (R) / Division (F) / Measure (D):*

There are three options random, division and measure:

Random: This allows to array the selected object along the path in a specify point according to user's need.

Division: This allows to array automatically the selected object along the path by inputting the number of objects.

Measure: This allows to array automatically the selected object along the path by inputting the distance value.

For example, if we do not know the distance between objects but we know the objects quantity, we can select the option Division:

After select the option, a prompt message will display:



Enter the number: And we enter the value 11

After enter the value, a prompt message will display:

Pick a point on the curve as start point (Distribute from the end curve when selection is empty):

Then pick one of the end points of the curve:

After pick the point of the curve, you will get accurate result: And also you can repeat the same array option for the other blue central axis of the road.



Flatten Objects: Converts 3D geometry to a projected 2D representation.

Menu: Express>Modify> Flatten Objects0

Command Entry: Flatten

7. Draw Tools

Superhatch: Fills an enclosed area or selected objects with a hatch pattern, solid fill or gradient hatch.

Menu: Express>Draw>Superhatch

Command Entry: Superhatch

The Superhatch dialog box is displayed:


Image: Accesses the Select Image dialog box to specify the image for the hatch pattern.

Block: Opens the Superhatch_Insert dialog box to specify the block for the hatch pattern.

Xref Attach: Accesses the Select reference file dialog box for specifying an xref file for a hatch pattern.



WipeOut: Selects a wipeout object as a hatch pattern.

Select Existing: Selects an existing image, block, xref, or Wipeout as a hatch pattern.




For Images:

1. Open Superhatch dialog box.
2. Click Image... button, choose an image file, the Superhatch Imageraster dialog box is displayed.
3. Pick the OK button in the Superhatch Imageraster dialog box, specify insertion point, scale factor and angle of rotation.
4. The prompt *"Is the placement of this IMAGE acceptable [Yes/No]<yes>":*
5. Pick a point in the rectangle, press ENTER to finish.



For Blocks:

1. Open Superhatch dialog box.
2. Click the Block... button to access the Superhatch_Insert dialog box:
 - Block:** Click the Block... button to select a block in the current file.
 - File:** Pick the File... button to select a drawing file as the block
3. Select the block in the Defined Blocks dialog box and press OK.
4. Specify insertion point, scale factor and angle of rotation.





Command Line
Command: SUPERHATCH
InsertEnter block name or [?] <NEW BED>: NEW BED
Unit: Millimeters convert: 1.0000
Specify insertion point or [Basepoint/Scale/X/Y/Z/Rotate]:
Enter X scale factor, specify opposite corner, or [Corner/X/Y/Z] <1>: Enter Y scale factor <use X scale factor>:
Specify rotation angle <0>:
Specify insertion point:
Enter X scale factor <1.000000>:
please appoint the rotate angle:
Is the placement of this BLOCK acceptable? [Yes/No]<Yes>Y
please appoint the first point:
Command:

5. The prompt *"Is the placement of this IMAGE acceptable? [Yes/No] <yes> "* is displayed. Choose No to Esc. If you choose Yes, GstarCAD will ask you to specify the first point and the next point to place the image.
6. Specify an internal point of the objects for hatch boundary then press ENTER to finish hatch.

For WipeOut:

1. Access Superhatch dialog box and click the Wipeout button:
2. GstarCAD will ask you to specify insertion point to create an area that masks underlying objects.
3. Press ENTER to finish creating the boundary that masks underlying objects.
4. As shown in the picture, move the new block to the carpet, the block will automatically cover the object under it:



Breakline Symbol: Creates a polyline and inserts the breakline symbol. The options within this command are provided to control the relative size and appearance of the breakline symbol and an extension of the polyline beyond the selected start and end points.

Menu: Express>Draw>Breakline Symbol

Command Entry: BREAKLINE

Once start the command, the command line prompts as follow:



Block = BRKLINE.DWG, Size = 1.000, Extension = 1.250 .

Specify first point for breakline or [Block/Size/Extension/sPecify line for breakline]:

Specify a point, or enter options

Options:

Specify first point for breakline: Draws break line through specifying its start point and end point.



Block: Determines the block to be used as the breakline symbol.

Enter the block name for breakline symbol <BRKLINE.DWG>: Enter a block name and press ENTER or press ENTER. If you press ENTER directly, the saving path of the break symbol file will be displayed on the command line.

Size: Determines the size of the breakline symbol.




Breakline symbol size <1>: Specify the size of the breakline symbol

Extension: Determines the length of the line extension beyond selected points.

Breakline extension distance <1.25>: Specify the extension distance. Once the start point for the break line or the setup break symbol is assigned, the command line prompts as follows:

Specify second point for breakline: Specify a point

Specify location for break symbol <Midpoint>: Specify the point on the line segment to specify the location of the breakline symbol, or press ENTER to use the midpoint of the line.



Spline to Line: Converts spline(s) to numbers of straight lines.

Menu: Express>Draw> Spline to Line

Command Entry: SPLINE2LINE

Once the command is started, the command line prompts as follow:




Select spline or [Set parameters(S)]: Select spline(s) or input "S" to set parameters

[The line precision/Starting point (S) <1.00>]: Input a new value bigger than 0 to join precision between segment lines

Conversion in a straight line to allow the greatest number of <5000>]: Input a new value smaller than 5000 to number of lines

At first, the system will fit the spline with a segment line which precision (Length) has been specified, if the line's number needed is more than the maximum number, the system will extend the length of the lines by force, using the maximum number of lines to fit the spline.

Select spline or [Set parameters(S)]: Then select the spline(s) to be converted and press Enter to finish the operation




Spline to Pline: With this tool the Spline created can be converted to a polyline according to the accuracy (number of segments of the arc) that the user assigns. The more specified the segment number is, the higher is the matching degree between the converted Polyline.

Menu: Express>Draw>Spline to Pline

Command Entry: SPTPL


For example, draw the follow spline sample with 5 arcs as shown:



After the command SPTPL is started, *Please select the object* (Spline).

After selecting the object, a prompt message will be displayed > *Delete the spline? Yes(Y) / No(N)*: In this case, if we select Yes, this option will delete the spline in place but if we select No, it will keep the spline.

After inputting the delete spline option, a prompt message will be displayed > *Please enter the number of arcs Non-zero*: And we have to input a value higher than zero, for example 8. This value determines the segment number of arcs to be created in the new Polyline.




Line to Pline: This function can convert one or multiple connected straight line(s), arc(s) to one polyline.

Menu: Express>Draw>Line to Polyline


Command Entry: Line2pl

After starting the command, a prompt message will be displayed> *Please enter the join precision: 0*




The Join precision will determine the union space between end points of each object. In this case, we will input value 0 to ensure the connection between objects (lines).

After inputting the join value, *Please select the objects to be joined* and converted to Polyline:



And finally, you have successfully created a polyline:



8. Tools


Command Alias: This function allows users to add, modify, delete command alias and shell commands.

Menu: Express > Tools > Command Alias

Command Entry: ALIAS

Operation steps:


1. Start the command and a dialog box will pop up.
2. Select commands to be deleted and click "Remove" button to delete command alias.
3. Select the command to be modified and click "Edit" button, a dialog box will pop up.
4. Click "OK" to finish editing.



System Variable Editor: Allows you to view, save, load and compare system variable settings.

Menu: Express > Tools > System Variable Editor

Command Entry: SYSVDLG



System Variables Dialog Box Options:

List Box: Displays a list of system variables. The edit field above the list box allows for filtering the list box display based on user input. For example, entering DIM* in the edit field filters the list to display only system variables that start with DIM. If nothing is entered in the edit field, the list displays all system variables. If more than one system variable is highlighted, all edit and display options are unavailable.

New Value: Displays the current value of the system variable highlighted in the list box and allows you to edit that

value. No changes are committed until the dialog is closed with the OK button.

Current Value: Displays the value of the system variable highlighted in the list box as if SYSVDLG was started.

Initial Value: Displays the initial value of the system variable highlighted in the list box. This is the value the system variable has in a new drawing.

Saved In: Displays where the value of the highlighted system variable is saved.

Type: Displays the type of the highlighted system variable; for

example, integer, real, string, and so on.

Save All: Saves the current system variable settings to an SVF or SCR file. SVF files can be read into SYSVDLG and SCR files are AutoCAD scripts that can be run from the AutoCAD command line. The button will display Save All, Save Selected or Save Filtered depending on the condition of the system variable list.

Read: Restores saved settings from an SVF file. No changes are saved to the drawing until you choose OK. All pending changes can be discarded with the Cancel button. SYSVDLG will validate new system variable values as they are changed.


Compare with saved: Compares the variables of the drawing with the saved SCR file.

Make Linetype: Creates a linetype based on selected objects.

Menu: Express > Tools > Make Linetype

Command Entry: MKLTYPE

Once the command is started, the following window will be displayed. You can find the Line files (*.lin) and apply them to the current drawing.



Make Shape: Creates a shape definition based on selected objects.

Menu: Express > Tools > Make Shape

Command Entry: MKSHAPE

Attach Xdata: Attaches extended object data (xdata) to a selected object.

Menu: Express > Tools > Attach Xdata

Command Entry: XDATA

List Object Xdata: Lists the xdata associated with an object.

Menu: Express > Tools > List Object Xdata

Command Entry: XDLIST

Break Point Check: It can mark unclosed endpoints among selected lines, polylines or arcs, and close them immediately when prompting that the area is not closed when hatching, calculating areas, or creating regions.

Menu: Express > Tools > Break Point Check

Command Entry: CLOSELINE

9. Table Tools


Table Fill In: You can use this function to fill in the table or edit the texts.

Menu: Express>Table Tools>Table Fill In

Command Entry: FORMTXT

Operation steps:

1. Start the command.
2. Click in the cell or input "Q" and a dialog box will pop up.
3. In the dialog box you can set the text height fashion, just fashion and other text attributes.
4. Click the blank area of a cell and input texts directly.
5. Enter to finish filling in.



Draw Table: This function can help you draw a table.

Menu: Express>Table Tools> Draw Table

Command Entry: BGE


Operation steps:

1. Start the command.
2. Specify the first point of the table.
3. The command line prompts.
 - a. Press Q key and the width of the form will increase a little, is used to adjust the horizontal width.
 - b. Press W key and the width of the form will decrease a little, used to adjust the horizontal width.
 - c. Press A key and the height of the form will increase a little, used to adjust the vertical height.
 - d. Press S key and the height of the form will decrease a little, used to adjust the vertical height.
4. You can input the corresponding options to adjust the size of the table.
5. Specify the second point to finish drawing the table.

Merge Cells: This function is similar to merge cells in Excel.

Menu: Express>Table Tools>Merge Cells


Command Entry: BGH




Operation steps:

1. Start the command.
2. Specify the borderline of the form to merge or the first cell, as shown below.
3. Merging effect as below. And press Enter to finish the command.

Sample1: Specify the borderline of the form



Sample2: Specify the first cell and another cell




Split Cells: This function is similar to split cells in Excel.

Menu: Express>Table Tools>Split Cells

Command Entry: BGFG

Operation steps:

1. Start the command.
2. Specify the cell which needs to be split.
3. Move the cursor, when the rows and columns are a size up. Click the mouse and the cell will be split automatically.



Add Bias: This function can add bias for a cell.


Click the start and end point according to the prompts and the system will provide an intersection snap and can easily find the start and end point of the bias, or you can click any area in one cell and the system will find the top left point of the cell automatically, then the system will prompt you to select the end point, you can also click any area in the cell, system will take the bottom right point as the end point automatically, this way, a bias is added in a cell.

Menu: Express>Table Tools>Add Bias

Command Entry: BGX

Operation steps:

1. Start the command.
2. Specify start point, you can click the top left point or click the blank area in the cell.
3. Specify end point to finish drawing the bias.



Drag Multiple Lines: You can change the row and column width by dragging the line of the table and the corresponding parts of the

line will also change. For example, drag the line you selected to the right side and all the lines in the right side will move to the right side correspondingly.

Menu: Express>Table Tools>Drag Multiple Lines

Command Entry: BGMT

Operation steps:

1. Start the command.
2. Specify the line of table for dragging.
3. Specify the place or distance to drag to (left is positive).
4. Enter to finish moving.

Drag Line: Different to Multiline drag, Drag line will just move the line you selected and other relevant lines will not move.

Menu: Express>Table Tools>Drag Line

Command Entry: BGST

Operation steps:

1. Start the command.
2. Specify the line of the table for dragging.
3. Specify the place or distance to drag to (left is positive).
4. Enter to finish the command.

Drag Segment: This command will not change the lines of the whole table, but just move the side line of a cell.

Menu: Express>Table Tools>Drag Segment

Command Entry: BGJT

Operation steps:

1. Start the command.
2. Specify the line of the table for dragging.
3. Specify the place or distance to drag (left is positive).
4. Enter to finish the command.




Selection Scale: This function can zoom in and zoom out the whole table base on the point you specified.

Menu: Express>Table Tools>Selection Scale

Command Entry: BGSF

Operation steps:

1. Start the command and specify the base point for the line of table.
2. Move the cursor and the table will zoom.
3. Drag to a suitable position and click.




Add Row: This function can add rows to the table.

Menu: Express>Table Tools>Add Row

Command Entry: BGZH

Operation steps:

1. Start the command.
2. Specify the position of the new row.
3. The system will add a row below the point you specified.




Add Column: This function can add new columns to the table.

Menu: Express>Table Tools>Add Column

Command Entry: BGZL

Operation steps:

1. Start the command.
2. Specify the direction of the new column.
3. The system will add a new column on the right side of the table.




Delete Row: This function can delete the row of the table you specified.

Menu: Express>Table Tools>Delete Row

Command Entry: BGSH

Operation steps:



1. Start the command and specify the cell of row for delete.
2. The system will delete the row you specified.



Delete Column: This function can delete columns you specified.

Menu: Express>Table Tools>Delete Column

Command Entry: BGSL

Operation steps:

1. Start the command.
2. Specify the cell of column for delete.
3. The system will delete the column you specified.




Delete Table: This function can delete the table you selected.

Menu: Express>Table Tools>Delete Table

Command Entry: BGSC

Operation steps:

1. Start the command and specify the table for delete.
2. Enter to finish deleting.



Text Orientation Adjust: This function is used to adjust the alignment of the texts.

Menu: Express>Table Tools>Text Orientation Adjust

Command Entry: BGJS

Operation steps:

1. Start the command and select the text for adjust.
2. Press Enter and the command line will prompt the location mode.
3. Here we input "1" to select left alignment.
4. The text you specified will align to the left, as shown below.

GstarCAD	GstarCAD	GstarCAD
GstarCAD	GstarCAD	GstarCAD
GstarCAD	GstarCAD	GstarCAD

```
Command Bar
Command: BGJS
*Text orientation adjust*=Bgjs
Select the text for adjust:
Select objects:Find out 1, total 1
Select objects:
Enter new justification...(0 Center,1 Left,2 Right,3 Both)<flush center>:
```

GstarCAD	GstarCAD	GstarCAD
GstarCAD	GstarCAD	GstarCAD
GstarCAD	GstarCAD	GstarCAD

Note:

- This function can only orient and adjust the table text in the TABLE layer.
- The distance to the table line using left alignment or right alignment has already been set by the program, if you think that the distance is not suitable, you can use the GstarCAD command to adjust the distance.


CAD Table to Excel: This command will convert sheets, composed by line/Spline and text/Mtext in CAD, to EXCEL.

Menu: Express>Table Tools> CAD Table to Excel

Command Entry: GC_CTE

Operation method:

1. Start the command and specify the conversion ratio.
2. Select the table that need to be changed and press enter, the system will automatically open EXCEL after conversion.
3. Save the EXCEL sheet.



PART LIST									
11	BMW-C-11	SMALL BUSHINGS	3	STEEL					Welded ITEM 1-B
10	BMW-C-10	SHAFT	1	Q235A					
9	BMW-C-9	SUB - BASE PLATE	1	STEEL					16mm thickness
8	BMW-C-8	MULTI-HOLE BASE PLATE	1	STEEL					16mm thickness
7	BMW-C-7	THREADED SHAFT	1	Q235A					Welded ITEM 8
6	BMW-C-6	BUSHING "B"	2	Q235A					Welded ITEM 5
5	BMW-C-5	SUPPORT PLATE	1	STEEL					15.5mm thickness
4	BMW-C-4	BUSHING "A"	1	Q235A					Welded ITEM 5
3	BMW-C-3	BMW - THREADED PIN "B"	1	Q235A					M12 x 1.4 x 104
2	BMW-C-2	BMW - THREADED PIN "A"	1	Q235A					M12 x 2.0 x 100
1	BMW-C-1	TLT PLATE	1	STEEL					16mm thickness
ITEM NO	PART NO		NOMENCLATURE OR DESCRIPTION		QTY	MATERIAL	HEAT TREATMENT	REMARKS	
PARTS LIST									
INIT	APPROVALS	DATE	INIT	APPROVALS	DATE	GSTARCAD			
ARP	Alonso Pizari	9/11							
						TITLE			
						BMW CHASSIS CLAMP			
						ASSEMBLY			
						SIZE	CAGE CODE	DWG NO	REV
						A2		BVM/CP-10006394	
						SCALE			SHEET

A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	R	S
PART LIST																		
1	11	BMW-C-11	SMALL BUSHINGS							3	STEEL	Welded ITEM 1-B						
2	10	BMW-C-10	SHAFT							1	Q235A							
3	9	BMW-C-9	SUB - BASE PLATE							1	STEEL	16mm thickness						
4	8	BMW-C-8	MULTI-HOLE BASE PLATE							1	STEEL	16mm thickness						
5	7	BMW-C-7	THREADED SHAFT							1	Q235A	Welded ITEM 8						
6	6	BMW-C-6	BUSHING "B"							2	Q235A	Welded ITEM 5						
7	5	BMW-C-5	SUPPORT PLATE							1	STEEL	15.5mm thickness						
8	4	BMW-C-4	BUSHING "A"							1	Q235A	Welded ITEM 5						
9	3	BMW-C-3	BMW - THREADED PIN "B"							1	Q235A	M12 x 1.4 x 104						
10	2	BMW-C-2	BMW - THREADED PIN "A"							1	Q235A	M12 x 2.0 x 100						
11	1	BMW-C-1	TLT PLATE							1	STEEL	16mm thickness						
12	ITEM NO		PART OR IDENTIFYING NO					NOMENCLATURE OR DESCRIPTION					QTY	MATERIAL	HEAT TREATMENT		REMARKS	
13	PARTS LIST																	
14	INIT	APPROVALS		DATE	INIT	APPROVALS		DATE		GSTARCAD								
15	ARP	Alonso Pizari		9/11														
16																		
17																		
18																		
19																		
20																		
21																		
22																		
23																		
24																		
25																		
26																		
27																		
28																		
29																		
30																		
31																		
32																		
33																		
34																		
35																		
36																		
37																		
38																		
39																		
40																		
41																		
42																		
43																		
44																		
45																		
46																		
47																		
48																		
49																		
50																		
51																		
52																		
53																		
54																		
55																		
56																		
57																		
58																		
59																		
60																		
61																		
62																		
63																		
64																		
65																		
66																		
67																		
68																		
69																		
70																		
71																		
72																		
73																		
74																		
75																		
76																		
77																		
78																		
79																		
80																		
81																		
82																		
83																		
84																		
85																		
86																		
87																		
88																		
89																		
90																		
91																		
92																		
93																		
94																		
95																		
96																		
97																		
98																		
99																		
100																		
101																		
102																		
103																		
104																		
105																		
106																		
107																		
108																		
109																		
110																		
111																		
112																		
113																		
114																		
115																		
116																		
117																		
118																		
119																		
120																		
121																		
122																		
123																		
124																		
125																		
126																		
127																		
128																		
129																		
130																		
131																		
132																		
133																		
134																		
135																		
136																		
137																		
138																		
139																		
140																		
141																		
142																		
143																		
144																		
145																		
146																		
147																		
148																		
149																		
150																		
151																		
152																		
153																		
154																		
155																		
156																		
157																		
158																		
159																		
160																		
161																		
162																		
163																		
164																		
165																		
166																		
167																		
168																		
169																		
170																		
171																		
172																		
173																		
174																		
175																		
176																		
177																		
178																		
179																		
180																		
181																		
182																		
183																		
184																		
185																		
186																		
187																		
188																		
189																		
190																		
191																		
192																		
193																		
194																		
195																		
196																		
197																		
198																		
199																		
200																		
201																		
202																		
203																		
204																		
205																		
206																		
207																		
208																		
209																		
210																		
211																		
212																		
213																		
214																		
215																		
216																		
217																		
218																		
219																		
220																		
221																		
222																		
223																		
224																		
225																		
226																		
227																		
228																		
229																		
230																		
231																		
232																		
233																		
234																		
235																		
236																		
237																		
238																		
239																		
240																		
241																		
242																		
243																		
244																		
245																		
246																		
247																		
248																		
249																		
250																		
251																		
252																		
253																		
254																		
255																		
256																		
257																		
258																		
259																		
260																		
261																		
262																		
263																		
264																		
265																		
266																		
267																		
268																		
269																		
270																		
271																		
272																		
273																		
274																		
275																		
276																		
277																		
278																		
279																		
280																		
281																		
282																		
283																		
284																		
285																		
286																		
287																		
288																		
289																		
290																		
291																		
292																		
293																		
294																		
295																		
296																		
297																		
298																		
299																		
300																		
301																		
302																		
303																		
304																		
305																		
306																		
307																		
308																		
309																		
310																		
311																		
312																		
313																		
314																		
315																		
316																		
317																		
318																		
319																		
320																		
321																		
322																		
323																		
324																		
325																		
326																		
327																		
328																		
329																		
330																		
331																		
332																		
333																		
334																		
335																		
336																		
337																		
338																		
339																		
340																		
341																		
342																		
343																		
344																		
345																		
346																		
347																		
348																		
349																		
350																		
351																		
352																		
353																		
354																		
355																		
356																		
357																		
358																		
359																		
360																		
361																		
362																		
363																		
364																		
365																		
366																		
367																		
368																		
369																		
370																		
371																		
372																		
373																		
374																		
375																		
376																		
377																		
378																		
379																		
380																		
381																		
382																		
383																		
384																		
385																		
386																		
387																		
388																		
389																		
390																		
391																		
392																		
393																		
394																		
395																		
396																		
397																		
398																		
399																		
400																		
401																		
402																		
403																		
404																		
405																		
406																		
407																		
408																		
409																		
410																		
411																		
412																		
413																		
414																		
415																		
416																		
417																		
418																		
419																		
420																		
421																		
422																		
423																		
424																		
425																		
426																		
427																		
428																		
429																		
430																		
431																		
432																		
433																		
434																		
435																		
436																		
437																		
438																		
439																		
440																		
441																		
442																		
443																		
444																		
445																		
446																		
447																		
448																		
449																		
450																		
451																		
452																		
453																		
454																		
455																		
456																		
457																		
458																		
459																		
460																		
461																		
462																		
463																		
464																		
465																		
466																		
467																		
468																		
469																		
470																		
471																		
472																		
473																		
474																		
475																		
476																		
477																		
478																		
479																		
480																		
481																		
482																		
483																		
484																		
485																		
486																		
487																		
488																		
489																		
490																		
491																		
492																		
493																		
494																		
495																		
496																		
497																		
498																		
499																		
500																		
501																		
502																		
503																		
504																		
505																		
506																		
507																		
508																		
509																		
510																		
511																		
512																		
513																		
514																		
515																		
516																		
517																		
518																		
519																		
520																		
521																		
522																		
523																		
524																		
525																		
526																		
527																		
528																		
529																		
530																		
531																		
532																		
533																		
534																		
535																		
536																		
537																		
538																		
539																		
540																		
541																		
542																		
543																		
544																		
545																		
546																		
547																		
548																		
549																		
550																		
551																		
552																		
553																		
554																		
555																		
556																		
557																		
558																		
559																		
560																		
561																		
562																		
563																		
564																		
565																		
566																		
567																		
568																		
569																		
570																		
571																		
572																		
573																		
574																		
575																		
576																		
577																		
578																		
579																		
580																		
581																		
582																		
583																		

10. Coordinate Tools

Export Coordinate: It is easier to extract coordinate data from drawing with COEXPORT innovative tool.

Menu: Express>Coordinate Tools>Export Coordinate

Command Entry: COEXPORT

You can pick as many points as you need from your drawing and export all the coordinate data to .txt or .xls file. This tool could be applied conveniently on planning, surveying, mapping, and construction drawings.

Execute COEXPORT command and select what format (.txt/.xls) you want to save the file. Then pick all the coordinate points on your current drawing. Each time you pick a point, its data will be automatically storage in the file you selected. To finish the process, press Enter. You can open the saved file and check out all coordinate data (X,Y,Z) extracted.

File name:

Save as type:



A1		f_x X	
	A	B	C
1	X	Y	Z
2	4166.793	3581.064	0
3	4176.993	3596.544	0
4	4196.193	3632.784	0
5	4221.512	3620.664	0
6	4216.473	3611.184	0
7	4241.552	3562.824	0
8	4244.793	3552.624	0
9	4100.673	3519.264	0
10	4067.073	3553.104	0
11	4033.953	3540.264	0
12	4018.713	3551.304	0
13	4111.473	3699.864	0
14	4129.713	3689.784	0

Coordinate Point: Dimensions the point coordinate in the drawing.


Menu: Express>Coordinate Tools>Coordinate Point

Command Entry: DIMCORD

- Using leaders instead of lines, when ungrouped, moving the text block will also move the leader line, allowing for more flexible placement of the dimension text, as shown below:



- Support adjustments for Scale and Text Height in the “Parameters” dialog box. These settings also remember the last used values, making repeated operations more efficient. The interface is shown below:




- Options for Group and Auto Switch.
 - When Group is checked, the generated coordinate dimensions will be grouped. If unchecked, they will be created as separate objects.
 - When Auto Switch is checked, GstarCAD automatically adjusts the direction of the text and leader line if they intersect, improving readability.

Change Z Coordinate: Choose several objects at one time and then change the Z coordinates together.


Menu: Express>Coordinate Tools>Change Z Coordinate

Command Entry: CHANGEZ



11. Drawing Tools

Graphic Compare: As we know the drawing compare function in GstarCAD can be used to compare similar drawings containing nearly number of drawn objects to each other, especially to compare different versions of revision drawings.





Menu: Express>Drawing Tools>Graphic Compare

Command Entry: OCMF


Drawing compare can make comparisons between two similar drawings (old DWG and New DWG) and generate them as separate files. After pressing COMPARE button within CompareDwg dialog box, the program will generate and open _old and _new.dwg files, where you can see the differences between drawings.

Drawing Compare can find out differences (drawn objects) and show the result with different colors, e.g. if a line is modified, removed or newly drawn, it will be displayed in different colors.



But there is something else that drawing compare could not accomplish so accurately. Drawing compare can't insert and show the compared objects on the current drawing working space that you are working at real time. Besides, drawing compare can't show the details of how the objects were located before they were modified.

So the details are very important when comparing objects. Now the new and innovative Graphic Compare tool can do more! It does not only compare two drawings with similar



objects geometry and find out the differences but also display the details of any change at the current workspace of your drawing in real time, e.g. if a line is modified, only the changed part of the line is displayed in different color. The unchanged part remains unchanged.

Graphic compare dialog box

You can invoke the Graphic Compare dialog box by typing OCMP command at command line or by dynamic input.

Specify Drawing: Offerstwo options of drawing comparison between select objects on your current drawing or specify files.

Select Objects: Offers two options of objects selection including their base points to be compared.

Select base objects and base point: This option allows select all objects including a basis point as a first selection set to be compared.

Select compare objects and base point: This option allows select all objects, including a basis point as a second selection set to be compared with the first selection set.



Specify File: Checkingthis option allows browse two drawing file to be compared known as base and compare file.

Output Drawing: Offers two options of drawing compared output.

Insert current document: This option allows insert the compared set of selected objects on the current workspace.


Export to a file: This option allows output the compared set of selected objects to a drawing file.

Output settings: You can setup properties like layer, color and linetype for all selected objects to be compared to enhance visual differences between them.




Inserting Compared Objects Set into Current Drawing


To insert compared objects set into current drawing, first select the button **Select base objects and base point**. Then select all objects as first selection set called base objects and specify a base point for the base objects. Then select the button **Select compare objects and base point** and repeat all previous process mentioned above.





DC REVISION "A"



DC REVISION "A"



Under Output Drawing, check the option **Insert current document**. If you want setup visual properties for the compared objects, click Output settings button. After that you can place the compared objects set in a convenient point according your need.




Drawing Compare: Drawing compare is an exclusive function in GstarCAD which is added according to the user's requirement. It enhances collaboration by using color-coded displays to show items on a drawing that have been changed, added, or deleted by other members of the design team. Changes to items such as styles, block attribute, object of block can also be tracked. The program will analyze the differences between two drawings automatically. Then the differences will be marked with different colors. Users can also set the marking color by clicking the "option" button.


Menu: Express>Drawing Tools>Drawing Compare

Command Entry: CMP


Once the command is started, the following window will be displayed:





In this window, you have to browse the old DWG (original drawing) and the new DWG (drawing modified). You can also assign a path to save the compared drawing. Then select the button Option to set-up the comparison parameters.



After setting up the comparison parameters such as: colors, layers, line type, etc. select Ok to confirm these parameters. Note: Pay attention to the mark color because the deleted, modified and added objects will assume these into the compared drawing. Then select the button Compare in the window below to compare both drawings.






Drawing Lock: Process some objects or the entire drawing into an uneditable state, and add the function of setting a password to lock the objects. The processed drawing can be browsed and printed, but cannot be decomposed or edited.

Menu: Express>Drawing Tools>Drawing Lock

Command Entry: LOCKUP

After enabling the **LOCKUP** command, follow prompts are displayed:



Objects will not be able to be modified after using this function, would you like to continue? [Yes(Y)/No(N)]: Confirms whether to continue executing the command.


Select Object: Selects objects that you want to lock in the drawing. If any of them is already locked, the “1 was on a locked layer” prompt will be displayed in the command line.

Do you want to create a password [Yes(Y)/No(N)]: Asks whether to add a password after locking objects.

Enter password: Inputs the password you set for the locked objects.

Note:

- The locked objects can be selected as trim boundaries to unlocked objects.
- The locked objects are turned into a block reference, and displayed on a temporary layer.
- The locked objects can be select. A little lock mark displays when you hover the cursor on a locked object.
- When executing the ERASE command to delete the locked objects, the delete command cannot be executed, and the “1 was on a locked layer” prompt



will be displayed in the command line.

- Versions that lower than GstarCAD may can not unlock the objects which locked with password.

Drawing Unlock: Unlocks the locked objects with the LOCKUP command to restore the locked object to an editable state.


Menu: Express>Drawing Tools>Drawing Unlock

Command Entry: UNLOCK

Drawing Merge: Drawing Merge searches frames of selected drawings and merge them into one drawing.

Menu: Express>Drawing Tools>Drawing Merge

Command Entry: AUTOMERGE



After inserting drawings, this feature analyzes and splits drawings as needed before merging them via external references. Users can configure settings such as the maximum columns, horizontal and vertical interval, alignment method, and whether to delete the split files at the current drawing's location. Additionally, users can view entity data from the drawings through "File Properties" and export the list of drawings to a .lst file.

Batch Purge (Batch Files Cleaning): This new function allows to batch purge the excess objects such as blocks, layers, line type, dimension style or text style on several DWG files. The Batpurge tool doesn't need to open files. It executes the command of purge directly, which makes it run with very high efficiency.

Menu: Express>Drawing Tools>Batch Purge

Command Entry: Batpurge

After the command is started, a dialog box will be displayed. In this dialog box you can add, select, unselect, clean and start purging objects within DWG files with the following options:

Add Files: Add one or more batch files from the selected path.

Add Folder: Add DWG files from a selected folder.

Select All: Select all the DWG file lists at once.


Select None: Unselect all the DWG files at once.

Delete: Delete selected object(s) in the file list.

Clear: Clean all the DWG file lists at once.

Start Purge: Starts purging the selected DWG file list. After purging, GstarCAD will generate a notepad file where you can see the purge details.

Log: After the purge operation is finished, you can Login in to the created notepad file and see the batch purge detail record.



Move BAK: Changes the destination folder for drawing backup (BAK) files.

Menu: Express>Drawing Tools> Move BAK

Command Entry: MOVEBAK

MOVEBAK command changes the destination folder for drawing backup (BAK) files. Once you specify a path, the drawing's BAK files is placed in that path after every save operation.

Enter new value for MOVEBAK, or for none <current setting>:

Enter a . (period) for none or type the folder name

If you enter ".", the MOVEBAK folder name is cleared and new BAK files will be created in the original folder.

12. AutoXlsTable



Create Table: Imports, modifies and updates a CAD table made in Excel spreadsheet to GstarCAD.

Menu: Express>AutoXlsTable>Create Table

Command Entry: _CAOT_AUTOXLSTABLE_CREATE

Operation steps:

1. In the AutoXLSTable pull-down menu, click Create Table.
2. Create an Excel spreadsheet or open an existing Excel spreadsheet in Excel.
3. Click Finish button in the AutoXlsTable pull-down menu in Excel.
4. Specify insertion point in GstarCAD.



19									
	A	B	C	D	E	F	G	H	I
1	PART LIST ABC- ASSEMBLY DRAWING REXROT								
2									
3	ABC-REXROT 38		1	CARBON STEEL					
4	ABC-REX- PT39		3	CARBON STEEL					
5	ABC-REX- PT40		1	CARBON STEEL					
6	ABC-REX- PT41		5	CARBON STEEL					
7	ABC-REX- PT42		7	CARBON STEEL					
8	ABC-REX- PT43		3	CARBON STEEL					
9	ABC-REX- PT44		2	CARBON STEEL					
10	ABC-REX- PT45		10	CARBON STEEL					
11	ABC-REX-TP321		7	MILD STEEL					
12	ABC-REX-TP322		4	CARBON STEEL					
13	ABC-REX-TP323		1	CARBON STEEL					
14	ABC-REX-TP324		1	CARBON STEEL					
15	ABC-REX-TP325		1	CARBON STEEL					
16	DESCRIPTION	SERIAL	QT	MATERIAL	TREATMENT	OBS	GSTARCAD ABC-ASSEMBLY DRAWING REXROT		
17									

Edit Table: Runs Excel and edits the table.


Menu: Express>AutoXlsTable>Edit Table

Command Entry: _CAOT_AUTOXLSTABLE_EDIT



Operation steps:

1. Click Edit Table.
2. Select a table created by AutoXlsTable in GstarCAD then the Excel file will open.



	A	B	C	D	E	F	G	H	I
1	PART LIST ABC- ASSEMBLY DRAWING REXROT								
2									
3	ABC-REXROT 38		1	MILD STEEL					
4	ABC-REX- PT39		3	MILD STEEL					
5	ABC-REX- PT40		1	MILD STEEL					
6	ABC-REX- PT41		5	MILD STEEL					
7	ABC-REX- PT42		7	MILD STEEL					
8	ABC-REX- PT43		3	MILD STEEL					
9	ABC-REX- PT44		2	MILD STEEL					
10	ABC-REX- PT45		10	MILD STEEL					
11	ABC-REX-TP321		7	MILD STEEL					
12	ABC-REX-TP322		4	MILD STEEL					
13	ABC-REX-TP323		1	MILD STEEL					
14	ABC-REX-TP324		1	MILD STEEL					
15	ABC-REX-TP325		1	MILD STEEL					
16	DESCRIPTION	SERIAL	QT	MATERIAL	TREATMENT	OBS	GSTARCAD ABC-ASSEMBLY DRAWING REXROT		


Update Table: Update table whose original Excel spreadsheet was modified.

Menu: Express>AutoXlsTable>Update Table

Command Entry: _CAOT_AUTOXLSTABLE_UPDATETBL

Operation steps:

1. Click Update table.
2. Select the table to update then the table will update automatically according to the relevant Excel.



	A	B	C	D	E	F	G	H	I
1	PART LIST ABC- ASSEMBLY DRAWING REXROT								
2									
3	ABC-REXROT 38		1	MILD STEEL					
4	ABC-REX- PT39		3	MILD STEEL					
5	ABC-REX- PT40		1	MILD STEEL					
6	ABC-REX- PT41		5	MILD STEEL					
7	ABC-REX- PT42		7	MILD STEEL					
8	ABC-REX- PT43		3	MILD STEEL					
9	ABC-REX- PT44		2	MILD STEEL					
10	ABC-REX- PT45		10	MILD STEEL					
11	ABC-REX-TP321		7	MILD STEEL					
12	ABC-REX-TP322		4	MILD STEEL					
13	ABC-REX-TP323		1	MILD STEEL					
14	ABC-REX-TP324		1	MILD STEEL					
15	ABC-REX-TP325		1	MILD STEEL					
16	DESCRIPTION	SERIAL	QT	MATERIAL	TREATMENT	OBS	GSTARCAD ABC-ASSEMBLY DRAWING REXROT		

	A	B	C	D	E	F	G	H	I
1	PART LIST ABC- ASSEMBLY DRAWING REXROT								
2									
3	ABC-REXROT 38		1	MILD STEEL					
4	ABC-REX- PT39		3	MILD STEEL					
5	ABC-REX- PT40		1	MILD STEEL					
6	ABC-REX- PT41		5	MILD STEEL					
7	ABC-REX- PT42		7	MILD STEEL					
8	ABC-REX- PT43		3	MILD STEEL					
9	ABC-REX- PT44		2	MILD STEEL					
10	ABC-REX- PT45		10	MILD STEEL					
11	ABC-REX-TP321		7	MILD STEEL					
12	ABC-REX-TP322		4	MILD STEEL					
13	ABC-REX-TP323		1	MILD STEEL					
14	ABC-REX-TP324		1	MILD STEEL					
15	ABC-REX-TP325		1	MILD STEEL					
	DESCRIPTION	SERIAL	QT	MATERIAL	TREATMENT	OBS	GSTARCAD ABC-ASSEMBLY DRAWING REXROT		

Update All the Tables: Updates the data of the table after the drawing was modified.

Menu: Express>AutoXlsTable>Update All the Tables

Command Entry: CAOT_AUTOXLSTABLE_UPDATEALLTBL

After executing this command, the system will update all the table objects created by “Create Table” command.


File Link Management: You can use this function to edit, manage the link relation between a table object and an external EXCEL file.

Menu: Express>AutoXlsTable>File Link Management

Command Entry: CAOT_AUTOXLSTABLE_MANAGELINK

Operation steps:


1. Start the command.
2. Select table object in the drawing and a dialog box will pop up.
3. Click the “Browse” button to open the file selection dialog box.
4. Select an XLS file which needs to be connected with a table object and click “OK”, then return to the Link Manager dialog box.
5. You can use the “Attach”, “Delete” and “Update” button to complete link related editing and management.



Path Settings: This function is used to set the path of an Excel file.

Menu: Express>AutoXlsTable>Path Settings

Command Entry: CAOT_AUTOXLSTABLE_USINGPATH



Operation steps:

1. Start the command and a dialog box will pop up as below.
2. In the dialog box, you can set the path pattern of the Excel file.


Selection Management: You can use this function to calculate objects length and area, when the length and area change, the calculating data will update automatically.

Menu: Express>AutoXlsTable>Selection Management


Command Entry: CAOT_AUTOXLSTABLE_SELECTION




Purpose: use the "Selection Management" function to calculate the area of a circle and a rectangle, when length and area change, the calculating data will update automatically.

1. Draw a circle and a rectangle as below, use the "Create Table" function to create a table as below.





2. Start the "Selection Management" command and a dialog box will pop up.
3. Input "CIRCLE" and click the "New Group" button.
4. Select the circle.
5. Press enter, the "Selection Management" dialog box will add a new item "CIRCLE", as shown below.
6. You can add a "RECTANGLE" item using the same operation as above.
7. Click "Close" to exit "Selection Management".
8. Use the "Edit Table" command to edit the table.
9. Click the cell on the right side of "CIRCLE" and click the "Insert Function" icon, as shown below:
10. In the dialog box, you can specify the entity as "CIRCLE", Layer as "All" and click "OK".





11. Use the same operation to insert the rectangle area calculating function. Then Click the pull-down menu “Finish” option of AutoXisTabl as shown.
12. Back to CAD and the table will calculate the area of the circle and rectangle.
13. Scale the rectangle and the table data will change automatically.



13. GstarCAD Tools


Drawing Scale: You can set the drawing scale before drawing, when you are using other tools (for example “Line Such as Chord” and “Modify Line width”), our software will adjust the scale automatically.

Menu: Express>GstarCAD Tools>Drawing Scale

Command Entry: SASCL

Operation steps:

1. Start the command.
2. Input a drawing ratio and enter to finish.



Rotate Cursor:

0: Rotates the cursor counterclockwise 0°.

Menu: Express>GstarCAD Tools>Rotate Cursor>0

Command Entry: RTCUR0

45: Rotates the cursor counterclockwise 45°.

Menu: Express>GstarCAD Tools>Rotate Cursor>45

Command Entry: RTCUR45


Side Line: Aligns the X axis of the cursor with the selected reference line segment.

Menu: Express>GstarCAD Tools>Rotate Cursor>Side Line

Command Entry: RTCUR1

Operation steps:

1. Start the command.
2. Select the reference segment and system will align the X axis of the cursor to the selected segment.



Real Time Rotate: Rotates cursor in real time.

Menu: Express>GstarCAD Tools>Rotate Cursor>Real Time Rotate

Command Entry: RTCUR

Operation steps:

After executing the command, the command line prompts as below.

You can use the AWSD four keys to control the cursor direction until you are satisfied and press enter.




Draw Axonometric Line: Using this function can easily draw an axonometric drawing.

Menu: Express>GstarCAD Tools>Draw Axonometric Line

Command Entry: SALPL

Operation steps:

1. Start the command and input the line width value.
2. The command line will prompt as below, input corresponding options, you can use it to switch between 0 degree and 45 degree and you can also input any angle value. Then press Enter to finish the command.




Visual Extension: Normally after extension, the extension effect will be displayed, but Visual Extension can display the effect in real time until you confirm the position.

Menu: Express>GstarCAD Tools>Visual Extension

Command Entry: ETT

Operation steps:

1. Start the command.
2. Select the line that needs to be extended, the system will choose the nearest side you clicked as extension side automatically.
3. Move the cursor and the segment will extend in real time.




Normal Connect: The Normal Connect function is similar to zero distance chamfer, it can delete the lines of actual intersection or apparent intersection parts.

Menu: Express>GstarCAD Tools>Normal Connect

Command Entry: GXFILT

Operation steps:

1. Start the command.
2. Select the first line segment.
3. Select the second line.
4. The result will be as shown in the picture.




Flex Connect: This function can extend or cut down the line to the actual intersection or apparent intersection point.

Menu: Express>GstarCAD Tools>Flex Connect

Command Entry: GXFSS


Operation sample:

1. Start the command.
2. Select the elongation (or shortening) of the line.



Super Fillet: This function can not only do the fillet operation but can also unify the filleted line layer, color and line type and the unified standard will take the first selected fillet object as reference.

Menu: Express>GstarCAD Tools>Super Fillet
Command Entry: SFILLET



Operation steps:


1. Start the command and input fillet radius.
2. Choose the first segment, as shown below. After executing the command, the layer, color, line type of another line and fillet will match with the first segment.
3. Choose the second segment.

Modify Linewidth: Modify the line width you specified, if what you specified is a line and our software will convert the line to Pline automatically and change the line width. This function is similar to the pedit function, we can use it as a shortcut version and it is very convenient for modifying the line width.

Menu: Express>GstarCAD Tools>Modify Linewidth
Command Entry: LCW

Operation steps:

1. Start the command.
2. Select the line.
3. Enter a new line width value and here we input “2” for example.
4. Enter to finish and the effect will be as shown in the picture.




Cross to Break: In engineering drawings, many places need to break the cross line. If we do this the original way, it will be very complex. Using this function breaking lines can be easily done.

Menu: Express>GstarCAD Tools>Cross to Break
Command Entry: CBK

Operation steps:

1. Start the command.
2. Specify the occluded line.
3. Choose the occluded (to be disconnected) line and what you selected will be cut off automatically.
4. Enter to finish the command.




Control Break Width: This function is used to set break width for cross objects.

Menu: Express>GstarCAD Tools>Control Break Width

Command Entry: CBKWID

Operation steps:

1. Start the command.
2. Enter the width of the break space.




Modify Text: In here you can find several tools to modify text properties.

Text Height: Changes the text height of single-line text object.

Menu: Express>GstarCAD Tools>Modify Text>Text Height

Command Entry: TXT40

1. Start the command.
2. Select a single line text.
3. Input text height.
4. Press enter to finish the command.




Width Factor: Changes the width factor of the text in single-line text object.

Menu: Express>GstarCAD Tools>Modify Text>Width Factor

Command Entry: TXT41

1. Start the command.
2. Select a single line text.
3. Input Width height ratio.
4. Press enter to finish the command.




Angle: Changes the angle of a single-line text object.

Menu: Express>GstarCAD Tools>Modify Text>Angle

Command Entry: TXT50

1. Start the command.
2. Select a single line text.
3. Input rotation angle.
4. Press enter to finish the command.




Obliquing Angle: Different to the rotation angle, after executing the command, the text will get an inclination deformation effect.

Menu: Express>GstarCAD Tools>Modify Text>Obliquing Angle

Command Entry: TXT51

1. Start the command.
2. Select a single line text.
3. Input tilt angle.
4. Press enter to finish the command.



Options Modify: You can use this function to modify all the options above.

Menu: Express>GstarCAD Tools>Modify Text>Options Modify

Command Entry: EDTXT



Super Axonometric: It is a quintessential function that can easily convert a plan drawing to an axonometric drawing.

Menu: Express>GstarCAD Tools>Super Axonometric

Command Entry: ZC

Operation steps:

1. Start the command.
2. Select objects and press enter, as shown below.
3. Enter the axonometric point of view, such as 45 degree.
4. The effect will be as below.



14. Plot Tools


Print PLT: Users can send PLT files to printer for printing.

Menu: Express>Plot Tool>Print PLT

Command Entry: PrintPlt

Operation Steps:

1. Start the command.
2. Select PrintPlt.exe in the dialog box.
3. Double-click the PrintPlt.exe file, then the “Print” dialog box will be displayed, in the dialog box you can select printer or change settings.
4. Click the OK button, the “Open” dialog box will be displayed and you can select the printed file.




Batch Print: Batch print drawings with the same drawing frame attribute.

Menu: Express>Plot Tool>Batch Print

Command Entry: BP

Operation steps:

1. Start the command.
2. Specify the type of frame. You can select Layer/ Block/ Polyline so that the system can recognize the frame.
3. Corner select the frame you want to print, you will get a dialog box.
4. Set the print Parameters, click “OK” to execute bath print.




Arrange Frame Automatically: This function can search frames automatically calculate according to the size of the frame and then arrange several drawings to a big drawing.

Menu: Express>Plot Tool>Arrange Frame Automatically

Command Entry: FRAMEAR

Operation steps:

1. Start the command, a dialog box will pop up.
2. In order to get a reasonable drawing plot arrangement, you can choose which industry you want to use in advance. Click “Options” and you will get a dialog box.



3. Click “Insert files”, an “Add file Manner” dialog box will pop up, you can set the manner you like to add to the file.



Folder: This option will add all the DWG files from the root directory to the arranged list, if you check “File that contains subfolders” option and all the DWG files from subfolders will be added to the arranged list.


Drawing list: Add specified LST file list.

File: Add specified DWG file.

4. After selecting, all the files will be in the list.

5. Click the “Preview” button to preview the arrangement effect. The system will arrange the drawings intelligently according to the frame above.

6. If you are satisfied with the effect, you can click “OK”, and then the system will arrange the drawings and insert the drawing frames into the current file.





GstarCAD 2027

<https://www.gstarcad.net>

Gstarsoft