



Network License Manager

GstarCAD 2025




Table of Contents

1.	GstarCAD Network License Manager Installation and Settings	3
1.1.	Installation	3
1.2.	Settings	5
2.	GstarCAD Network License Activation and Return	7
2.1.	Online Activate	7
2.2.	Manual Activate	9
2.3.	Online Return	12
2.4.	Manual Return	13
3.	Check The Users Who Activated The Network License from Your Server	17
4.	Check the Users Who Borrowed the Network License from Your Server.....	18
5.	Check the Users Who are using /were used the network license	19

GstarCAD 2025 Network License Manager Guide


GstarCAD Network License encryption mode enables you to share a number of GstarCAD licenses on your office LAN. It gives flexibility of license floating among a working group. Before the network installation, you should specify the server computer to install [GstarCAD 2025 Network License Manager](#).

1. GstarCAD Network License Manager Installation and Settings


1.1. Installation

Please follow the steps below to install and set the configurations:


1. Double click "[glm-Setup](#)" to install [GstarCAD 2025 Network license Manager](#).




2. You can choose whether start the server immediately or start it later.




3. You will find a tray icon with exclamation mark shown in the taskbar after installation has been completed. And there will be a tips like "Service is not found. Please check your settings" before you set the configurations.



4. Click [GstarCAD Network License Manager](#) icon and click [Options](#) to set the configurations



5. Set the configurations as below:



System:

Run this server when Windows startup: When this options is checked, GstarCAD License Manager can be restarted automatically when Windows startup.

Remark: "Run this server when Windows startup" option will not affect the license status.

License service:

Log Path: You can specify a path to save the license logs and the path should allow LocalService to write in, otherwise the license service will fail to run. If your operation system is Windows 10, the default path ProgramData is recommended.

Service port: The valid range should among 1024-64000.

License Port: The valid range should among 27000-27009.


6. After the configurations have been set, the exclamation mark with change to check mark.




1.2. Settings

1. Click **GstarCAD Network License Manager** icon and select **License Manager** option to load license manager box.

You can activate, return the GstarCAD network licenses online or manually, you can repair the license when it shows error message in license manager. The users whom are sharing your network license and lend detail also can be found in license manager.



2. Feature list in License Manager.



Refresh: Refresh GstarCAD network license status.

Online Activate: Activate GstarCAD network license online.

Manual Activate: Manually Activate GstarCAD network license.

Online Return: Return GstarCAD network license online.

Manual Return: Manually return GstarCAD network license.

Online Repair: Repair GstarCAD network license online.


Manual Repair: Manually repair GstarCAD network license.

License Details: Shows the using license information in detail.

Borrowed Details: Shows the Network license borrowed information in detail.

Statistical Details: Displays user information for users who are using the license or the user information for users who used the license during a certain period of time.

3. Adjust GstarCAD Network License Service.




Start Service: Starts Gstarsoft License Service, other users whom with the permission can borrow or lend the licenses from the server.

Stop Service: Stop Gstarsoft License Service, other users whom with the permission will not allowed to borrow or lend the licenses from the server.


Restart Service: When the service meets some problems, you can try to restart it.

Note: If you need to do any changes on your license, please stop service first and restart service after the operation have been done.

4. Get the GstarCAD Network License Manager version information in [About](#).



5. Click [Exit](#) to quit GstarCAD Network License Manager.




2. GstarCAD Network License Activation and Return

If you have a GstarCAD 2025 Network License Key, you can run GstarCAD License Manager on server computer to manage your Network License, such as license activation, license return and so on.


2.1. Online Activate

Instruction: make sure your computer connect to the internet.

1. Click **GstarCAD License Manager** icon and select **License Manager** option.




2. Click **Online Activate** button.



3. Input the **License Key** and click **OK** button.




4. Then you will find the activated license shows in the license manager list.



Note: For Windows Server operation system, if it prompts "Session does not exist" when activate GstarCAD Network license online via GstarCAD Network License Manager, please check the following solution:

1. Open [Internet Explorer \(IE\)](#) and select [Internet Options](#) and then click [Trusted sites](#) from [Security](#) tab.



2. Add the following two sites to the trusted sites.

<https://support.gstarcad.net>


<https://support2.gstarcad.net>

3. Click **OK** button to save the security settings. Then you can activate or return GstarCAD network license online normally.


2.2. Manual Activate

Instruction: If your computer is not connected to the internet, you can use activation file (xml file) to activate your GstarCAD 2025 Network license manually.

1. Click **GstarCAD License Manager** icon and select **License Manager** option.




2. Click **Manual Activate** button.




3. Please follow the three steps in this dialog box to activate manually.

Steps 1:


- 1) Input the **License Key** and click **Create Request** button to generate the request file.






Steps 2:

- 1) Please access GstarCAD online service center: <https://license.gstarcad.net/> and login with the License Key from a computer with internet connection.



- 2) Then click **Activate** button in Activation tab.



- 3) Click the **Choose File** button and select the request file you have saved and click the **Submit** button to continue.

My License: 3401-E907-0700-0300-71CF-078F-71CA-0400

Request XML File

Choose File

Upload File: 3401-E907-0700-0300-71CF-078F-71CA-0400_ActivateRequest.xml

Load the credible request XML activation file which created at user client

Submit

Find out the file and click it to submit

- 4) Click the **Download** button and save the license file (Response XML File). We recommend you to store the license file to your USB flash drive.

My License: 3401-E907-0700-0300-71CF-078F-71CA-0400

Product	Encryption Type	Network License Node Quantity	License Type	Language	Service Period	License Status	Response XML
GstarCAD 2025 Plus	Network Version	3	Trial License	en-US	2024-06-04~2024-06-11	Activated	

Please download Response XML file to activate your product.
Please click "Return License" to return your license.

Steps 3:

Back to your computer and find out License manager option from GstarCAD Network License Manager. Please click the **Import Response** button and select the license file you have just downloaded and saved from another computer, and then click the **OK** button to finish the activation.

Activate new license

Input LicenseKey

3401-E907-0700-0300-71CF-078F-71CA-0400 **Create Request**

Enter license key, click 'Create Request' button to generate request file.
Send request file to your local distributor/reseller to get response file.

Import Response File


Click 'Import Response' button to import the response file. **Import Response**

Close


2.3. Online Return

Instruction: make sure your computer connect to the internet.

1. Select the license which you want to return and click the **Online Return** button.




2. After a few seconds, you can see the license you have selected to return has disappeared from License information.




Steps 1:

- 1) Click **Create Request** button to generate and save the request file.





Steps 2:

- 1) Please access GstarCAD online service center: <https://license.gstarcad.net/> and login with the **License Key**.




- 2) Then Click **License Management** tab, and click **Return License** button to upload the return file.








3) Choose the return request XML file you saved and click Submit to upload the return file.




4) **Download** the Response XML from License Management tab.



- 5) Back to your computer and find out GstarCAD License manager, please click the [Import Response](#) button and select the license file you have just downloaded and saved from another computer.




- 6) Click [OK](#) button to finish returning the GstarCAD network license.




3. Check The Users Who Activated The Network License from Your Server

GstarCAD network license supports a pool of licenses (nodes) on the server and users who have the authorization (server IP and license Port) can activate the corresponding version from their side in the same LAN. When a user quits GstarCAD 2025, the license will automatically be returned to license manager. From the License Details, you can see the network license activation information. Select the correct product and click [License Details](#) from License manager.





For example: If your network license has three nodes and three users activated and using currently, there will be no available nodes left for other users to activate or borrow. If one of the three activated users quits GstarCAD 2025, the node will be returned to license manager, and there will be one license available which can be activated or borrowed.



4. Check the Users Who Borrowed the Network License from Your Server



GstarCAD network license allows users to borrow nodes from the server for a certain period. The license manager list shows the number of borrowed nodes and the number of available nodes left. The Borrowed Details option shows the information about the borrowed nodes.

For example, if your network license has a total of three nodes, and one user has borrowed a node from the server, then there will only be two available nodes left that can be activated or borrowed. The borrowed license can be automatically returned to the server on the expiration date, or the user can return it manually at any time during the validity period.



5. Check the Users Who are using /were used the network license

You can check the users who are currently using a network license, as well as user information during a certain period of time via the Statistical Details Options in Network License Manager. It can filter the users who are currently using the licenses, as well as those who used the licenses by options "In User, Today, Yesterday, last 7 days and Specified Days".



Note:

1. Some security software (such as anti-virus software) may cause GstarCAD Network License Manager run abnormally; In this case, you can either quit the security software or add GstarCAD Network License Manager to the trusted path.
2. The server computer name should be in English.
3. If the server computer has an old GstarCAD License Manager installed, please turn it off first, then install the latest version of GstarCAD Network License Manager.



GstarCAD 2025



■ <https://www.gstarcad.net/>